

How to install ioncube on jump server?

7 admin March 11, 2025 [Installation](#) 46709

How to install ioncube on jumpserver or bastion host?

Overview: [IonCube Loader](#) is typically installed to enable PHP scripts encoded with IonCube to run on a server. These scripts are often proprietary or contain sensitive intellectual property and are encoded to protect them from unauthorized access or modification. By installing IonCube Loader, the server can interpret and execute these encoded scripts, allowing them to function as intended while maintaining their security measures.

The user needs root access to the server to configure Ioncube for PHP.

Step 1: Download the latest Ioncube version from the site mentioned below.

<https://www.ioncube.com/loaders.php>

Users would need to identify whether your **system architecture is 32-bit or 64-bit**. The subsequent command would help you with it.

```
root@gateway:~# file /bin/ping

/bin/ping: setuid ELF 64-bit LSB shared object, AMD x86-64, version 1
(SYSV), for GNU/Linux 2.6.9, stripped
```

As evident, the architecture is 64-bit.

Download the Ioncube package designed for 64-bit systems and extract it to /usr/local/ioncube.

```
root@gateway:~#
wget
https://downloads.ioncube.com/loader_downloads/ioncube_loaders_lin_x86-64.tar.gz

root@gateway:~# tar -zxf ioncube_loaders_lin_x86-64.tar.gz && mv
ioncube /usr/local
```

Step 2: Identify the PHP version you're running on your system.

```
root@gateway:~# php -v

PHP 8.1.26 (cli) (built: Nov 24 2023 08:49:33)
```

Step 3: Edit the PHP configuration file & add the corresponding Ioncube loader.

Load the Ioncube version corresponding to the PHP version running on the server.

Example: If the PHP Version is 8.1, The Ioncube loader should be ioncube_loader_lin_8.1.so

- **For RHEL 8:**

```
root@gateway:~# vi /etc/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.2.so

root@gateway:~# systemctl restart httpd
```

- **For Ubuntu 18:**

```
root@gateway:~# vi /etc/php/7.2/cli/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.2.so

root@gateway:~# vi /etc/php/7.2/apache2/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.2.so

root@gateway:~# systemctl restart apache2
```

- **For Ubuntu 20:**

```
root@gateway:~# vi /etc/php/7.4/cli/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.4.so


root@gateway:~# vi /etc/php/7.4/apache2/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.4.so


root@gateway:~# systemctl restart apache2
```

- **For Ubuntu 22:**

```
root@gateway:~# vi /etc/php/8.2/cli/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_8.2.so


root@gateway:~# vi /etc/php/8.2/apache2/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_8.2.so


root@gateway:~# systemctl restart apache2
```

- **For Ubuntu 24:**

```
root@gateway:~# vi /etc/php/8.2/cli/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_8.2.so


root@gateway:~# vi /etc/php/8.2/apache2/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_8.2.so


root@gateway:~# systemctl restart apache2
```

- **For Debian 9:**

```
root@gateway:~# vi /etc/php/7.0/cli/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.0.so


root@gateway:~# vi /etc/php/7.0/apache2/php.ini

zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.0.so


root@gateway:~# systemctl restart apache2
```

- **For Debian 10/11:**

```
root@gateway:~# vi /etc/php/7.3/cli/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.3.so
```

```
root@gateway:~# vi /etc/php/7.3/apache2/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.3.so
```

```
root@gateway:~# systemctl restart apache2
```

- **For SUSE LINUX 15:**

```
root@gateway:~# vi /etc/php7/cli/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.4.so
```

```
root@gateway:~# vi /etc/php7/apache2/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.4.so
```

```
root@gateway:~# apachectl restart
```

- **For Debian 9 Nginx:**

```
root@gateway:~# vi /etc/php/7.0/cli/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.0.so
```

```
root@gateway:~# vi /etc/php/7.0/fpm/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.0.so
```

```
root@gateway:~# systemctl reload nginx.service
```

```
root@gateway:~# systemctl reload php7.0-fpm.service
```

- **For Centos 7:**

```
root@gateway:~# vi /etc/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_8.1.so
```

```
root@gateway:~# systemctl restart httpd
```

- **For Centos 7 Nginx:**

```
root@gateway:~# vi /etc/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_8.1.so
```

```
root@gateway:~# systemctl restart nginx
```

- **For Centos 8:**

```
root@gateway:~# vi /etc/php.ini
```

```
zend_extension = /usr/local/ioncube/ioncube_loader_lin_7.2.so
```

```
root@gateway:~# systemctl restart httpd
```

Step 4: Check the PHP version again to see whether Ioncube has been loaded properly.

```
root@gateway:~# php -v

PHP 8.2.19 (cli) (built: May 13 2024 18:20:15) (NTS)
Copyright (c) The PHP Group
Zend Engine v4.2.19, Copyright (c) Zend Technologies
with the ionCube PHP Loader v13.0.2, Copyright (c) 2002-2023, by
ionCube Ltd.
with Zend OPcache v8.2.19, Copyright (c), by Zend Technologies
```

Step 5: Ensure that Ioncube decoders are loaded by viewing the PHP configuration page.

```
root@gateway:~# vi /var/www/html/info.php
```

```
<?php
phpinfo();
?>
```

Access the information page, and it will display the loaded Ioncube version. As observed, ionCube version 12.0.5 is currently loaded.

This program makes use of the Zend Scripting Language Engine:
Zend Engine v4.1.26, Copyright (c) Zend Technologies
with the [ionCube PHP Loader v12.0.5](#), Copyright (c) 2002-2022, by ionCube Ltd.
with Zend OPcache v8.1.26, Copyright (c), by Zend Technologies

zendengine

ionCube Loader

ionCube Loader developed by ionCube Ltd.
Visit [ioncube.com](#) for [latest Loaders](#) and [support](#)



Loader version	12.0.5
----------------	--------

Contact our [support department](#) if you face any further difficulties.



Setup your SSH jump server in 30 minutes

30 Days Free Trial



Related Articles:

[Install and switch different versions of PHP in Ubuntu](#)

[Upgrade PHP to 8.1 in Debian](#)

[Upgrade PHP to 8.2 in OpenSUSE 15](#)

Online URL: <https://www.ezeelogin.com/kb/article/how-to-install-ioncube-on-jump-server-7.html>