

# Switches & routers supports on Ezeelogin ssh jump server

557 Manu Chacko March 21, 2025 [Productivity & Efficiency Features](#) 808

## Switches & Routers supported in Ezeelogin

**Overview:** This article lists the switches and routers supported in Ezeelogin, including Huawei, Fortinet, and Cisco devices, and provides commands to check their software versions and SSH server status.

Most Switches and routers that support standard SSH 2 protocol would work if you [add them with the "Keep Server Password"](#) option.

### Find the router versions that support Ezeelogin.

- USG6500E- Huawei Versatile Routing Platform Software VRP (R) Software, Version 5.170 (USG6500E V600R007C20SPC600) RTOS Version 207.6
- Huawei Router with Version 20, SPC600
- Fortinet- Fortigate 100D, 100E, 100F, 60D, 60E, 60F

### Find the command to find the version of HUAWEI Router & Switches

Run the **display version** command to view the switch software version.

```
<HUAWEI> display version
Huawei Versatile Routing Platform Software
VRP (R) software, Version 5.160 (S7700 V200R007C00)
Copyright (C) 2000-2013 HUAWEI TECH CO., LTD
Quidway S7703 Terabit Routing Switch uptime is 0 week, 0 day, 1 hour, 3 minutes
BKP 0 version information:
1. PCB Version : LE02BAKB VER.A
2. Supporting PoE : No
3. Board Type : ES0B017712P0
4. MPU Slot Quantity : 2
5. LPU Slot Quantity : 3
```

### Display the global configuration on the SSH server.

```
<Huawei> display ssh server status
SSH version                :2.0 SSH connection timeout          :120 seconds SSH server key generatin
g interval :0 hours SSH Authentication retries          :3 times SFTP Server                :Enable Stelnet
server                  :Enable
```

```
<Huawei> display ssh server session
```

	Conn	Ver	Encry	State	Auth-type
Username-----	VTY 0	2.0	AES128_CBC	run	
password john-----					

## Find the command to find the version of Fortinet-Fortigate Router & Switches

```
FortiRouter # get system status
Version: FortiGate-100E v7.2.10,build1706,240918 (GA.M)
Security Level: 2
Firmware Signature: certified
```

## Find the command to find the version of CISCO Router & Switches

Run the **show version** command to view the switch/router software version.

```
SW1# show version
Cisco IOS Software, C2960 Software (C2960-LANBASEK9-M), Version 15.0(2)SE4, RELEASE
SOFTWARE (fc1)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2013 by Cisco Systems, Inc.
Compiled Wed 26-Jun-13 02:49 by mnnguyen

ROM: Bootstrap program is C2960 boot loader
BOOTLDR: C2960 Boot Loader (C2960-HBOOT-M) Version 12.2(25r)FX, RELEASE SOFTWARE
(fc4)

Switch uptime is 39 minutes
System returned to ROM by power-on
System image file is "flash:c2960-lanbasek9-mz.150-2.SE4.bin"
```

### Related Articles:

[Manage ssh access to Routers and Switch in Ezeelogin](#)

Online URL:

<https://www.ezeelogin.com/kb/article/switches-routers-supports-on-ezeelogin-ssh-jump-server-557.html>