


# Configure a replica LDAP/AD Server

794 Nesvin KN September 27, 2025 [Tweaks & Configuration](#) 247

## How to configure replica Active Directory or OpenLDAP server in Ezeelogin for high availability?

**Overview:** This article explains how to configure replica LDAP ( OpenLDAP) / Active Directory (AD) servers in Ezeelogin to ensure automatic failover if the primary LDAP server becomes unavailable, helping you avoid downtime.



### Steps to add/edit replica LDAP server URIs:

**Step 1:** Open the LDAP configuration. Go to Settings -> LDAP -> LDAP Settings


**Step 2:** In the URI(s) field, add or edit the LDAP server addresses. Enter the replica LDAP server URIs, separated by spaces, after the primary server URI.

**Step 3:** Click Save to apply the settings.

**Add more than one replica LDAP servers by entering the LDAP URIs separated by spaces.**

**Example:**

```
ldap://ad1.eznoc.com ldap://ad2.eznoc.com ldap://ad3.eznoc.com ldap://ad4.eznoc.com .....
```



## Example:

If the primary LDAP/Active Directory server is **ad1.eznoc.com** and the replica server is **ad2.eznoc.com**, configure the LDAP URI as follows (separating the URIs with spaces):

```
ldap://ad1.eznoc.com ldap://ad2.eznoc.com
```

For SSL-enabled LDAP (LDAPS), use:

```
ldaps://ad1.eznoc.com ldaps://ad2.eznoc.com
```

This ensures that if **ad1.eznoc.com** becomes unreachable, Ezeelogin will automatically fail over to **ad2.eznoc.com**.

## Related Articles:

[Integrate OpenLDAP / Windows Active Directory authentication in Ezeelogin jump server](#)

[Configure Ezeelogin to authenticate using Windows\\_AD\(Pam-Ldap\) in ubuntu?](#)

[How to configure Ezeelogin to authenticate using Open\\_Ldap\(Pam-Ldap\) in Ubuntu?](#)

[Integrate Windows AD with Ubuntu using SSSD](#)

Online URL: <https://www.ezeelogin.com/kb/article/configure-a-replica-ldap-ad-server-794.html>