Setting global values for gateway users and remote servers

709 Jisna Joseph April 26, 2025 Features & Functionalities 3108


How to set parameters globally for gateway users and remote servers in Ezeelogin?

Overview : This article explains how to set commonly used values in remote servers and gateway user section globally, so that these parameters need not to be configured everytime.


1. USER SECTION

1 A: Enabling Pass User Through

When "**Pass User Through**" is enabled, SSH gateway users will be logged in to the remote servers with the same username as SSH gateway user. When "**inherit**" option is selected the value will be taken from the global Settings, which is located under **settings -> general -> miscellaneous -> Pass User Through**.




Enabling/Disabling Pass User Through in global settings under **settings -> general -> miscellaneous -> Pass User Through,** will be applied to the user when the '**Inherit**' option is selected.




2. SERVER SECTION

2 A: Use DNS

When **Use DNS** is enabled, Ezeelogin will try to resolve the server hostnames using DNS instead of taking the IP provided in Ezeelogin to SSH into the remote server. On selecting '**inherit**' option the global values are used which is under **settings** -> **general** -> **miscellaneous** -> **Use DNS.**




Enabling/Disabling **Use DNS** in global settings, which is under **settings** -> **general** -> **miscellaneous** -> **Use DNS,** will be applied to servers when the '**Inherit**' option is selected.



2 B: CP Use DNS

If CP Use DNS is enabled, Ezeelogin will try to resolve the server hostnames using DNS instead of taking the IP provided in Ezeelogin for auto-login to **control panel**. When ’**inherit**’ option is selected the value is taken from the global settings which is under **settings** -> **general** -> **miscellaneous** -> **CP Use DNS**



Enabling/Disabling **CP Use DNS** in global settings, which is under **settings** -> **general** -> **miscellaneous** -> **CP Use DNS,** will be applied to servers when the '**Inherit**' option is selected.

Related Articles:

Enable and disable DNS for server hostname while adding in servers and for control panel access

Pass User through

Online URL: https://www.ezeelogin.com/kb/article/setting-global-values-for-gateway-users-and-remote-servers-709.html